



TUNE Into Reading™ 8.0 Minimum System Requirements

Local Area Network	100-megabit LAN minimal, 1000-megabit (1GB) LAN preferred. Each loaded exercise averages 10 to 14 megabytes in size per student session.
Internet Access	Access to *.elpcorp.com requiring access through TCP ports 80 (http) and 443 (https). A high-speed Internet connection is required. Load is dependent upon the number of students which use TUNE into Reading™ during a given session.
Application URL	https://tir.elpcorp.com/
Proxy / Cache Settings	Proxy / cache should be configured to allow optimal incoming and outgoing traffic to *.elpcorp.com .
Antivirus / Internet Security / Content Filters	All firewalls, antivirus, and content filters must be be configured with the proper rules and exclusions for both the TIR app and to allow traffic to *.elpcorp.com (ports 80 and 443 respectively)

	Workstation Requirements
Operating System	Microsoft Windows 7, 8, 8.1, 10 / MAC OS X 10.10 Yosemite, 10.11 El Capitan, MAC OS 10.12 Sierra, MAC OS 10.13 High Sierra, MAC OS 10.14 Mojave Google Chromebooks with Chrome OS 74 and up iPads with iOS version 12.1.1 or greater
CPU	Windows & MAC computers - Intel Pentium or Core class CPU of at least 2.0 GHz speed or better is recommended. Chromebooks with Intel Pentium or Core class CPU of 1.5GHz speed or better is recommended. (Celeron, Atom, or other 'word-processing only' CPUs are not supported.)
Memory	At least 4 gigabytes of RAM or greater is recommended.
Video Resolution	1024x768 or greater resolution is required.
Video Memory	At least 128MB video RAM
Input and Output	USB Headset with built-in microphone preferred. Chromebooks, Android and iPad devices may require analog ¼ jack for headset with mic. Or USB to analog audio adapter.
Disk Space	200 megabytes during installation. 300 megabytes total during use.
Requirements	Windows & Mac desktops / laptops: TUNE Into Reading installer package (Download from https://tir.elpcorp.com) . Chromebooks and Android devices: Download the TUNE into Reading installer from Google Play store by searching for 'TUNE Into Reading'. iPads: Download the TUNE into Reading installer from Apple Store by searching for 'TUNE into Reading'.



Web Browser	Google Chrome, Microsoft Edge, Mozilla Firefox 6+, or any HTML5 compatible web browser which supports video playback.
Application Storage Directory on Local Hard Drive:	For Windows: Read / write access to the following: "C:\ProgramData\Electronic Learning Products*.*", "C:\Program Files (x86)\Tune Into Reading*.*", "C:\Users\%CURRENT USER%\AppData\Local\Electronic Learning Products*.*" For MAC: Read / write access to the following: "/Applications/TUNE Into Reading/", "/Users/Shared/ELP.TIR*/", "/%USER%/Application Support/*"

For further technical assistance, please contact us at 1-888-357-8863 or send us an e-mail at 'support@elpcorp.com'.